Table of Contents

Password Recovery Procedure for the GSS GUI Version 1.0	1
Document ID: 41883	1
Introduction	1
Before You Begin	1
Conventions	1
Prerequisites	1
Step-by-Step Procedure	1
Related Information	2
<u>Conventions</u> . <u>Prerequisites</u> <u>Step-by-Step Procedure</u> . <u>Related Information</u> .	1 1 2

Password Recovery Procedure for the GSS GUI Version 1.0

Document ID: 41883

Introduction Before You Begin Conventions Prerequisites Step-by-Step Procedure Related Information

Introduction

This document provides the password recovery procedure for Global Site Selector (GSS) GSS GUI Version 1.0.

Note: If the password recovery fails at any point, issue the **gss restart** command from the CLI. Issuing this command returns you to Step 1 of this document.

Before You Begin

Conventions

For more information on document conventions, see the Cisco Technical Tips Conventions.

Prerequisites

There are no specific prerequisites for this document.

Step-by-Step Procedure

Perform the steps below when an administrator loses the administrative username and password for the GUI on the GSS.

- 1. Log into the CLI as an administrator to the primary Global Site Selector Manager (GSSM).
- 2. Issue the **gss status** command on the GSSM. The output should state read GSS Manager primary.
- 3. In the CLI, type **cd** ../apache.
- 4. FTP or SCP the file **httpd.conf** to an external device that contains a text editor.
- 5. On the external device, open httpd.conf. Change AuthUserFile /cisco/merlot/safe-state/http-users to AuthUserFile /cisco/merlot/etc/http-users.default .
- 6. Place the edited file back on the GSS via FTP or SCP.

Note: Make sure the file is put back into the correct directory.

- 7. Issue the show processes | grep httpd | killall –HUP httpd command on the CLI.
- 8. Log in to the GUI. The username is admin, and the password is default.

- 9. Change the admin password in the GUI using Tools -> User Administration -> Edit (select the admin icon). Do not use the Change Password menu that is displayed as the default page under Tools.
- 10. Issue the **gss restart** command on the CLI to force the GSS to use the new admin account. You must enter this command before you can login with the new admin password. It may take a couple of minutes for the restart to finish (even though the prompt comes back fast). To find out the current status during this period, issue the **gss status** command on the CLI.

Note: While the GSS is restarting, it will not be responding to Domain Name System (DNS) queries. 11. Login with the username and password you entered in Step 9.

Related Information

- Content Networking Downloads (registered customers only)
- Content Networking Devices Hardware Support
- Technical Support Cisco Systems

All contents are Copyright © 1992–2005 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.

Updated: Mar 15, 2005

Document ID: 41883